# Avionics Reference Document David Knight July 2019

# Contents

| 1 | Introduction                                   | 5      |
|---|--|--------|
|   | 1.1 Purpose                                    | <br>5  |
|   | 1.2 Scope                                      | 5      |
|   | 1.3 Definitions and Acronyms                   | <br>5  |
| 2 | Hardware                                       | 6      |
|   | 2.1 Pressure                                   | <br>6  |
|   | 2.2 Temperature                                | <br>6  |
|   | 2.3 Electrical                                 | <br>6  |
|   | 2.4 Mechanical                                 | <br>6  |
| 3 | EEPROM Layouts                                 | 7      |
|   | 3.1 Layout Version IDs                         | <br>7  |
|   | 3.2 Sensor Board Layout Rev 1                  | 8      |
|   | 3.3 Power Distro Board Layout Rev 1            | <br>9  |
| 4 | CAN IDs  | 10     |
|   | 4.1 ID 0 - Clock Sync                          | <br>10 |
|   | 4.2 ID 1 - Emergency Signal                    | 10     |
|   | 4.3 ID 100 - Helium Pressure                   | 10     |
|   | 1.4 ID 101 - Lox Pressure                      | 10     |
|   | 4.5 ID 102 - Methane Pressure                  | 10     |
|   | 4.6 ID 103 - Chamber Pressure                  | 10     |
|   | 4.7 ID 200 - Helium Fill Valve                 | 10     |
|   | 4.8 ID 201 - LOX Fill Valve                    | 10     |
|   | 4.9 ID 202 - Methane Fill Valve                | 11     |
|   | 4.10 ID 300 - Helium Tank Temperature          | 11     |
|   | 4.11 ID 301 - LOX Tank Temperature             | 11     |
|   | 4.12 ID 302 - Methane Tank Temperature         | 11     |
|   | 4.13 ID 303 - Nozzle Temperature               | 11     |
|   | 4.14 ID 304 - Upper Air Frame Temperature      | 11     |
|   | 4.15 ID 400 - Helium PT Current                | 11     |
|   | 4.16 ID 401 - LOX PT Current                   | 11     |
|   | 4.17 ID 402 - Methane PT Current               | 12     |
|   | 4.18 ID 403 - Chamber PT Current               | 12     |
|   | 4.19 ID 404 - Helium Fill Hall Effect Current  | 12     |
|   | 4.20 ID 405 - LOX Fill Hall Effect Current     | 12     |
|   | 4.21 ID 406 - Methane Fill Hall Effect Current | 12     |

# List of Tables

# List of Figures

# 1 Introduction

- 1.1 Purpose
- 1.2 Scope
- 1.3 Definitions and Acronyms

# 2 Hardware

# 2.1 Pressure

| Measurement       | HE Tank Pressure    |
|-------------------|---------------------|
| Extension board # | 2                   |
| Model #           | MLH05KPSB01G        |
| Link              | Mouser Page         |
| Range             | 0 psig to 5000 psig |
| Accuracy          | $\pm 0.25\%$        |
| Temperature range | -40°C to +125°C     |
| Input Voltage     | 8VDC to 30VDC       |
| Output            | 1VDC to 5VDC        |
| Data Rate         | 50Hz                |

# 2.2 Temperature

# 2.3 Electrical

# 2.4 Mechanical

# 3 EEPROM Layouts

# 3.1 Layout Version IDs

| VersionID | Version Name                    |
|-----------|---------------------------------|
| 1         | Sensor Board Layout Rev 1       |
| 2         | Power Distro Board Layout Rev 1 |

# ${\bf 3.2}\quad {\bf Sensor\ Board\ Layout\ Rev}\ {\bf 1}$

|                      | Sensor Board Layout Rev 1 Page #0 |                      |                                |                          |       |  |  |  |  |
|----------------------|-----------------------------------|----------------------|--------------------------------|--------------------------|-------|--|--|--|--|
| Byte #               | Usage                             | Byte #               | Usage                          | Byte #                   | Usage |  |  |  |  |
| 0<br>1<br>2<br>3     | Board Status                      | 48<br>49<br>50<br>51 | Hall Effect 1<br>Current CanID | 96<br>97<br>98<br>99     |       |  |  |  |  |
| 4<br>5<br>6<br>7     | Board VIN Voltage<br>CanID        | 52<br>53<br>54<br>55 | Hall Effect 2 Data<br>CanID    | 100<br>101<br>102<br>103 |       |  |  |  |  |
| 8<br>9<br>10<br>11   | Board current CanID               | 56<br>57<br>58<br>59 | Hall Effect 2<br>Current CanID | 104<br>105<br>106<br>107 |       |  |  |  |  |
| 12<br>13<br>14<br>15 | PT0 Data CanID                    | 60<br>61<br>62<br>63 | TC0 Data CanID                 | 108<br>109<br>110<br>111 |       |  |  |  |  |
| 16<br>17<br>18<br>19 | PT0 Current CanID                 | 64<br>65<br>66<br>67 | TC0 Current CanID              | 112<br>113<br>114<br>115 |       |  |  |  |  |
| 20<br>21<br>22<br>23 | PT1 Data CanID                    | 68<br>69<br>70<br>71 | TC1 Data CanID                 | 116<br>117<br>118<br>119 |       |  |  |  |  |
| 24<br>25<br>26<br>27 | PT1 Current CanID                 | 72<br>73<br>74<br>75 | TC1 Current CanID              | 120<br>121<br>122<br>123 |       |  |  |  |  |
| 28<br>29<br>30<br>31 | PT2 Data CanID                    | 76<br>77<br>78<br>79 | RTD0 Data CanID                | 124<br>125<br>126<br>127 |       |  |  |  |  |
| 32<br>33<br>34<br>35 | PT2 Current CanID                 | 80<br>81<br>82<br>83 | RTD1 Data CanID                |                          |       |  |  |  |  |
| 36<br>37<br>38<br>39 | Hall Effect 0 Data<br>CanID       | 84<br>85<br>86<br>87 |                                |                          |       |  |  |  |  |
| 40<br>41<br>42<br>43 | Hall Effect 0<br>Current CanID    | 88<br>89<br>90<br>91 |                                |                          |       |  |  |  |  |
| 44<br>45<br>46<br>47 | Hall Effect 1 Data<br>CanID       | 92<br>93<br>94<br>95 |                                |                          |       |  |  |  |  |

# ${\bf 3.3}\quad {\bf Power~Distro~Board~Layout~Rev~1}$

|        | I                  | Power Distro   | Board Layout Rev | 1 Page #0 |       |
|--------|--------------------|----------------|------------------|-----------|-------|
| Byte # | Usage              | Byte #         | Usage            | Byte #    | Usage |
| 0      |                    | 48             |                  | 96        |       |
| 1      | Board Status       | 49             |                  | 97        |       |
| 2      | Board Status       | 50             |                  | 98        |       |
| 3      |                    | 51             |                  | 99        |       |
| 4      |                    | 52             |                  | 100       |       |
| 5      | Offboard Battery   | 53             |                  | 101       |       |
| 6      | Voltage CANID      | 54             |                  | 102       |       |
| 7      |                    | 55             |                  | 103       |       |
| 8      |                    | 56             |                  | 104       |       |
| 9      | Offboard Battery   | 57             |                  | 105       |       |
| 10     | Current CANID      | 58             |                  | 106       |       |
| 11     |                    | 59             |                  | 107       |       |
| 12     |                    | ff 60          |                  | 108       |       |
| 13     | Onboard Battery    | 61             |                  | 109       |       |
| 14     | Voltage CANID      | 62             |                  | 110       |       |
| 15     |                    | 63             |                  | 111       |       |
| 16     |                    | 64             |                  | 112       |       |
| 17     | Onboard Battery    | 65             |                  | 113       |       |
| 18     | Current CANID      | 66             |                  | 114       |       |
| 19     |                    | 67             |                  | 115       |       |
| 20     |                    | 68             |                  | 116       |       |
| 21     | Helix Loop Voltage | 69             |                  | 117       |       |
| 22     | CANID              | 70             |                  | 118       |       |
| 23     | CAND               | 71             |                  | 119       |       |
| 24     |                    | $\frac{1}{72}$ |                  | 120       |       |
| 25     | Helix Loop Current | 73             |                  | 121       |       |
| 26     | CANID              | 74             |                  | 122       |       |
| 27     | CANID              | 75             |                  | 123       |       |
| 28     |                    | 76             |                  | 124       |       |
| 29     |                    | 77             |                  | 125       |       |
| 30     |                    | 78             |                  | 126       |       |
| 31     |                    | 79             |                  | 127       |       |
| 32     |                    | 80             |                  | 121       |       |
| 33     |                    | 81             |                  |           |       |
| 34     |                    | 82             |                  |           |       |
| 35     |                    | 83             |                  |           |       |
| 36     |                    | 84             |                  |           |       |
| 37     |                    | 85             |                  |           |       |
| 38     |                    | 86             |                  |           |       |
| 39     |                    | 87             |                  |           |       |
| 40     |                    | 88             |                  |           |       |
| 40     |                    | 88             |                  |           |       |
| 41 42  |                    | 89<br>  90     |                  |           |       |
|        |                    |                |                  |           |       |
| 43     |                    | 91             |                  |           |       |
| 44     |                    | 92             |                  | []        |       |
| 45     |                    | 93             |                  |           |       |
| 46     |                    | 94             |                  |           |       |
| 47     |                    | 95             |                  | Ш         |       |

# 4 CAN IDs

# 4.1 ID 0 - Clock Sync

Frequency: 50Hz

| Byte | Bit | Signed | Range           | Units        | Description |
|------|-----|--------|-----------------|--------------|-------------|
| 0-3  |     | False  | 0 to 4294967295 | Milliseconds | UTC time    |

## 4.2 ID 1 - Emergency Signal

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units | Description   |
|------|-----|--------|-------|-------|---------------|
| 0    |     | False  |       |       | Status        |
|      | 0-1 |        |       |       | System Status |

#### 4.3 ID 100 - Helium Pressure

Frequency: 50Hz

|   | Byte | Bit | Signed | Range | Units        | Description     |
|---|------|-----|--------|-------|--------------|-----------------|
| ſ | 0-3  |     | False  |       | Milliseconds | UTC time        |
| Ì | 4-5  |     | False  |       | PSIG         | Helium Pressure |

#### 4.4 ID 101 - Lox Pressure

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units        | Description  |
|------|-----|--------|-------|--------------|--------------|
| 0-3  |     | False  |       | Milliseconds | UTC time     |
| 4-5  |     | False  |       | PSIG         | LOX Pressure |

#### 4.5 ID 102 - Methane Pressure

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units        | Description      |
|------|-----|--------|-------|--------------|------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time         |
| 4-5  |     | False  |       | PSIG         | Methane Pressure |

#### 4.6 ID 103 - Chamber Pressure

Frequency:  $50 \mathrm{Hz}$ 

| Byte | Bit | Signed | Range | Units        | Description      |
|------|-----|--------|-------|--------------|------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time         |
| 4-5  |     | False  |       | PSIG         | Chamber Pressure |

## 4.7 ID 200 - Helium Fill Valve

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description             |
|------|-----|--------|-------|--------------|-------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                |
| 4    |     | False  |       | Open/Closed  | Helium Fill Valve State |

#### 4.8 ID 201 - LOX Fill Valve

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description          |
|------|-----|--------|-------|--------------|----------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time             |
| 4    |     | False  |       | Open/Closed  | LOX Fill Valve State |

## 4.9 ID 202 - Methane Fill Valve

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description              |
|------|-----|--------|-------|--------------|--------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                 |
| 4    |     | False  |       | Open/Closed  | Methane Fill Valve State |

## 4.10 ID 300 - Helium Tank Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description             |
|------|-----|--------|-------|--------------|-------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                |
| 4-5  |     | True   |       | Celcius      | Helium Tank Temperature |

## 4.11 ID 301 - LOX Tank Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description          |
|------|-----|--------|-------|--------------|----------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time             |
| 4-5  |     | True   |       | Celcius      | LOX Tank Temperature |

## 4.12 ID 302 - Methane Tank Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description              |
|------|-----|--------|-------|--------------|--------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                 |
| 4-5  |     | True   |       | Celcius      | Methane Tank Temperature |

# 4.13 ID 303 - Nozzle Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description        |
|------|-----|--------|-------|--------------|--------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time           |
| 4-5  |     | True   |       | Celcius      | Nozzle Temperature |

#### 4.14 ID 304 - Upper Air Frame Temperature

Frequency: 10Hz

| rroquoi | .cj. 1011 | _      |       |              |                             |
|---------|-----------|--------|-------|--------------|-----------------------------|
| Byte    | Bit       | Signed | Range | Units        | Description                 |
| 0-3     |           | False  |       | Milliseconds | UTC time                    |
| 4-5     |           | True   |       | Celcius      | Upper Air Frame Temperature |

#### 4.15 ID 400 - Helium PT Current

Frequency:  $10 \mathrm{Hz}$ 

|   | Byte | Bit | Signed | Range | Units        | Description       |
|---|------|-----|--------|-------|--------------|-------------------|
| ĺ | 0-3  |     | False  |       | Milliseconds | UTC time          |
| ĺ | 4-5  |     | True   |       | milliamps    | Helium PT Current |

#### 4.16 ID 401 - LOX PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description    |
|------|-----|--------|-------|--------------|----------------|
| 0-3  |     | False  |       | Milliseconds | UTC time       |
| 4-5  |     | True   |       | milliamps    | LOX PT Current |

## 4.17 ID 402 - Methane PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description        |
|------|-----|--------|-------|--------------|--------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time           |
| 4-5  |     | True   |       | milliamps    | Methane PT Current |

#### 4.18 ID 403 - Chamber PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description        |
|------|-----|--------|-------|--------------|--------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time           |
| 4-5  |     | True   |       | milliamps    | Chamber PT Current |

#### 4.19 ID 404 - Helium Fill Hall Effect Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description                     |
|------|-----|--------|-------|--------------|---------------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                        |
| 4-5  |     | True   |       | milliamps    | Helium Fill Hall Effect Current |

#### 4.20 ID 405 - LOX Fill Hall Effect Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description                  |
|------|-----|--------|-------|--------------|------------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                     |
| 4-5  |     | True   |       | milliamps    | LOX Fill Hall Effect Current |

#### 4.21 ID 406 - Methane Fill Hall Effect Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units        | Description                      |
|------|-----|--------|-------|--------------|----------------------------------|
| 0-3  |     | False  |       | Milliseconds | UTC time                         |
| 4-5  |     | True   |       | milliamps    | Methane Fill Hall Effect Current |