Avionics Reference Document

David Knight
July 2019

Contents

| 1 | Intr | roduction | 5 |
|---|------------------------|--|----------|
| | 1.1 | Purpose | 5 |
| | 1.2 | Scope | 5 |
| | 1.3 | Definitions and Acronyms | 5 |
| 2 | Har | dware | 6 |
| | 2.1 | Pressure | 6 |
| | 2.2 | Temperature | 6 |
| | 2.3 | Electrical | 6 |
| | 2.4 | Mechanical | 6 |
| 3 | EEI | PROM | 7 |
| | 3.1 | Layout Version IDs | 7 |
| | 3.2 | Layout Sensor Board Layout Rev 1 | 8 |
| | 3.3 | Layout Power Distro Board Layout Rev 1 | 9 |
| 4 | $\mathbf{C}\mathbf{A}$ | N IDs | ١0 |
| | 4.1 | | 10 |
| | 4.2 | v | 10 |
| | 4.3 | | 10 |
| | 4.4 | | 10 |
| | 4.5 | | 10 |
| | 4.6 | | 10 |
| | 4.7 | | 10 |
| | 4.8 | ID 201 - LOX Fill Valve | 11 |
| | 4.9 | | 11 |
| | 4.10 | ID 300 - Helium Tank Temperature | 11 |
| | | | 11 |
| | 4.12 | ID 302 - Methane Tank Temperature | 11 |
| | 4.13 | ID 303 - Nozzle Temperature | 11 |
| | | | 11 |
| | 4.15 | | 11 |
| | 4.16 | | 12 |
| | 4.17 | ID 402 - Methane PT Current | 12 |
| | 4.18 | ID 403 - Chamber PT Current | 12 |
| | 4.19 | ID 404 - Helium Fill Hall Effect Current | 12 |
| | | | 12 |
| | | | 12 |

List of Tables

List of Figures

1 Introduction

- 1.1 Purpose
- 1.2 Scope
- ${\bf 1.3}\quad {\bf Definitions}\ {\bf and}\ {\bf Acronyms}$

2 Hardware

2.1 Pressure

| Measurement | HE Tank Pressure |
|-------------------|---------------------|
| Extension board # | 2 |
| Model # | MLH05KPSB01G |
| Link | Mouser Page |
| Range | 0 psig to 5000 psig |
| Accuracy | $\pm 0.25\%$ |
| Temperature range | -40°C to +125°C |
| Input Voltage | 8VDC to 30VDC |
| Output | 1VDC to 5VDC |
| Data Rate | 50Hz |

2.2 Temperature

2.3 Electrical

2.4 Mechanical

3 EEPROM

3.1 Layout Version IDs

| VersionID | Version Name |
|-----------|---------------------------------|
| 1 | Sensor Board Layout Rev 1 |
| 2 | Power Distro Board Layout Rev 1 |

${\bf 3.2}\quad {\bf Layout~Sensor~Board~Layout~Rev~1}$

| | Layout Sen | sor Board | Layout Rev 1 Page #0 | | |
|--------|-----------------------------|-----------|------------------------------|--------|----------|
| Byte # | Usage | Byte # | Usage | Byte # | Usage |
| 0 | | 48 | | 96 | Reserved |
| 1 | Layout Version ID (0x1) | 49 | Hall Effect 1 Data CanID | 97 | Reserved |
| 2 | Layout version 1D (0x1) | 50 | Tian Ellect I Data Camb | 98 | Reserved |
| 3 | | 51 | | 99 | Reserved |
| 4 | | 52 | | 100 | Reserved |
| 5 | Board Status | 53 | Hall Effect 1 Current CanID | 101 | Reserved |
| 6 | Doard Status | 54 | Tian Ellect I Current Camb | 102 | Reserved |
| 7 | | 55 | | 103 | Reserved |
| 8 | | 56 | | 104 | Reserved |
| 9 | D1 VIN V-14 CID | 57 | H-11 Efft 2 D-t- CID | 105 | Reserved |
| 10 | Board VIN Voltage CanID | 58 | Hall Effect 2 Data CanID | 106 | Reserved |
| 11 | | 59 | | 107 | Reserved |
| 12 | | 60 | | 108 | Reserved |
| 13 | December Comp | 61 | Hall Effect 9 Comment Coally | 109 | Reserved |
| 14 | Board current CanID | 62 | Hall Effect 2 Current CanID | 110 | Reserved |
| 15 | | 63 | | 111 | Reserved |
| 16 | | 64 | | 112 | Reserved |
| 17 | DTO Data C. ID | 65 | TICO Data C. ID | 113 | Reserved |
| 18 | PT0 Data CanID | 66 | TC0 Data CanID | 114 | Reserved |
| 19 | | 67 | | 115 | Reserved |
| 20 | | 68 | | 116 | Reserved |
| 21 | DES G G D | 69 | TC0 Current CanID | 117 | Reserved |
| 22 | PT0 Current CanID | 70 | | 118 | Reserved |
| 23 | | 71 | | 119 | Reserved |
| 24 | | 72 | TC1 Data CanID | 120 | Reserved |
| 25 | | 73 | | 121 | Reserved |
| 26 | PT1 Data CanID | 74 | | 122 | Reserved |
| 27 | | 75 | | 123 | Reserved |
| 28 | | 76 | | 124 | Reserved |
| 29 | | 77 | | 125 | Reserved |
| 30 | PT1 Current CanID | 78 | TC1 Current CanID | 126 | Reserved |
| 31 | | 79 | | 127 | Reserved |
| 32 | | 80 | | | |
| 33 | DEC D. G. ID. | 81 | DEED OF COMP | | |
| 34 | PT2 Data CanID | 82 | RTD0 Data CanID | | |
| 35 | | 83 | | | |
| 36 | | 84 | | | |
| 37 | DTTO C C . ID | 85 | Dan 1 D + C + D | | |
| 38 | PT2 Current CanID | 86 | RTD1 Data CanID | | |
| 39 | | 87 | | | |
| 40 | | 88 | Reserved | | |
| 41 | | 89 | Reserved | | |
| 42 | Hall Effect 0 Data CanID | 90 | Reserved | | |
| 43 | | 91 | Reserved | | |
| 44 | | 92 | Reserved | | |
| 45 | T 11 77 | 93 | Reserved | | |
| 46 | Hall Effect 0 Current CanID | 94 | Reserved | | |
| 47 | | 95 | Reserved | | |
| | <u> </u> | 1 | | Ш | 1 |

${\bf 3.3}\quad {\bf Layout~Power~Distro~Board~Layout~Rev~1}$

| | Layout Power Distro Board | | | | |
|--------|--------------------------------|--------|----------|--------|----------|
| Byte # | Usage | Byte # | Usage | Byte # | Usage |
| 0 | | 48 | Reserved | 96 | Reserved |
| 1 | Largert Vergion ID (0r2) | 49 | Reserved | 97 | Reserved |
| 2 | Layout Version ID (0x2) | 50 | Reserved | 98 | Reserved |
| 3 | | 51 | Reserved | 99 | Reserved |
| 4 | | 52 | Reserved | 100 | Reserved |
| 5 | D 1.C/ | 53 | Reserved | 101 | Reserved |
| 6 | Board Status | 54 | Reserved | 102 | Reserved |
| 7 | | 55 | Reserved | 103 | Reserved |
| 8 | | 56 | Reserved | 104 | Reserved |
| 9 | 0.00 | 57 | Reserved | 105 | Reserved |
| 10 | Offboard Battery Voltage CANID | 58 | Reserved | 106 | Reserved |
| 11 | | 59 | Reserved | 107 | Reserved |
| 12 | | 60 | Reserved | 108 | Reserved |
| 13 | | 61 | Reserved | 109 | Reserved |
| 14 | Offboard Battery Current CANID | 62 | Reserved | 110 | Reserved |
| 15 | | 63 | Reserved | 111 | Reserved |
| 16 | | 64 | Reserved | 1112 | Reserved |
| 17 | | 65 | Reserved | 113 | Reserved |
| 18 | Onboard Battery Voltage CANID | 66 | Reserved | 114 | Reserved |
| 19 | | 67 | Reserved | 115 | Reserved |
| | | 68 | | | |
| 20 | | | Reserved | 116 | Reserved |
| 21 | Onboard Battery Current CANID | 69 | Reserved | 117 | Reserved |
| 22 | · | 70 | Reserved | 118 | Reserved |
| 23 | | 71 | Reserved | 119 | Reserved |
| 24 | | 72 | Reserved | 120 | Reserved |
| 25 | Helix Loop Voltage CANID | 73 | Reserved | 121 | Reserved |
| 26 | I and | 74 | Reserved | 122 | Reserved |
| 27 | | 75 | Reserved | 123 | Reserved |
| 28 | | 76 | Reserved | 124 | Reserved |
| 29 | Helix Loop Current CANID | 77 | Reserved | 125 | Reserved |
| 30 | Henz Edop Current Crivid | 78 | Reserved | 126 | Reserved |
| 31 | | 79 | Reserved | 127 | Reserved |
| 32 | Reserved | 80 | Reserved | | |
| 33 | Reserved | 81 | Reserved | | |
| 34 | Reserved | 82 | Reserved | | |
| 35 | Reserved | 83 | Reserved | | |
| 36 | Reserved | 84 | Reserved | | |
| 37 | Reserved | 85 | Reserved | | |
| 38 | Reserved | 86 | Reserved | | |
| 39 | Reserved | 87 | Reserved | | |
| 40 | Reserved | 88 | Reserved | | |
| 41 | Reserved | 89 | Reserved | | |
| 42 | Reserved | 90 | Reserved | | |
| 43 | Reserved | 91 | Reserved | | |
| 44 | Reserved | 92 | Reserved | | |
| 45 | Reserved | 93 | Reserved | | |
| | | | Reserved | | |
| 46 | Reserved | 94 | Beserven | | |

4 CAN IDs

4.1 ID 0 - Clock Sync

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-----------------|--------------|-------------|
| 0-3 | | False | 0 to 4294967295 | Milliseconds | UTC time |

4.2 ID 1 - Emergency Signal

Frequency: 50 Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|-------|---------------|
| 0 | | False | | | Status |
| | 0-1 | | | | System Status |

4.3 ID 100 - Helium Pressure

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|-----------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | False | | PSIG | Helium Pressure |

4.4 ID 101 - Lox Pressure

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|--------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | False | | PSIG | LOX Pressure |

4.5 ID 102 - Methane Pressure

Frequency: 50Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | False | | PSIG | Methane Pressure |

4.6 ID 103 - Chamber Pressure

Frequency: $50 \mathrm{Hz}$

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | False | | PSIG | Chamber Pressure |

4.7 ID 200 - Helium Fill Valve

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|-------------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4 | | False | | Open/Closed | Helium Fill Valve State |

4.8 ID 201 - LOX Fill Valve

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|----------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4 | | False | | Open/Closed | LOX Fill Valve State |

4.9 ID 202 - Methane Fill Valve

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|--------------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4 | | False | | Open/Closed | Methane Fill Valve State |

4.10 ID 300 - Helium Tank Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|-------------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | Celcius | Helium Tank Temperature |

4.11 ID 301 - LOX Tank Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|----------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | Celcius | LOX Tank Temperature |

4.12 ID 302 - Methane Tank Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|--------------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | Celcius | Methane Tank Temperature |

4.13 ID 303 - Nozzle Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|--------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | Celcius | Nozzle Temperature |

4.14 ID 304 - Upper Air Frame Temperature

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|-----------------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | Celcius | Upper Air Frame Temperature |

4.15 ID 400 - Helium PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|-------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | milliamps | Helium PT Current |

4.16 ID 401 - LOX PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|----------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | milliamps | LOX PT Current |

4.17 ID 402 - Methane PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|--------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | milliamps | Methane PT Current |

4.18 ID 403 - Chamber PT Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|--------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | milliamps | Chamber PT Current |

4.19 ID 404 - Helium Fill Hall Effect Current

Frequency: 10Hz

| 1 | · . | | | | |
|------|-----|--------|-------|--------------|---------------------------------|
| Byte | Bit | Signed | Range | Units | Description |
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | milliamps | Helium Fill Hall Effect Current |

4.20 ID 405 - LOX Fill Hall Effect Current

Frequency: 10Hz

| Byte | Bit | Signed | Range | Units | Description |
|------|-----|--------|-------|--------------|------------------------------|
| 0-3 | | False | | Milliseconds | UTC time |
| 4-5 | | True | | milliamps | LOX Fill Hall Effect Current |

4.21 ID 406 - Methane Fill Hall Effect Current

Frequency: 10Hz

| | Byte | Bit | Signed | Range | Units | Description |
|--|------|-----|--------|-------|--------------|----------------------------------|
| | 0-3 | | False | | Milliseconds | UTC time |
| | 4-5 | | True | | milliamps | Methane Fill Hall Effect Current |